Setup Document

Setup Ubuntu in EC2

Use Ubuntu in EC2

Setup Jupyter Lab

Setup Airflow

Keep running Jupyter and Airflow

Resource

Setup Ubuntu in EC2

- Go to AWS EC2 and create an instance.
- Choose Ubuntu Server 18.04 and t3a.medium.
- Generate key pair.
- Launch it.
- Go to security group
- Add inbound rules
 - Type:Custom TCP, Port range:8888, Source:0.0.0.0/0, Description:Jupyter
 - o Type:Custom TCP, Port range:8080, Source:0.0.0.0/0, Description:Airflow

Use Ubuntu in EC2

- Open PowerShell.
- Go to the directory which contains the generated key pair.
- \$ ssh -i "KEYPAIR_PEM_NAME" ubuntu@[Public DNS (IPv4)]

Setup Jupyter Lab

- \$ sudo apt update
- \$ sudo apt upgrade
- \$ sudo apt install python3-pip
- \$ pip3 --version
- \$ sudo pip3 install --upgrade pip
- \$ pip3 --version
- \$ sudo apt install python3-dev
- \$ sudo -H pip3 install jupyter
- \$ jupyter notebook
 - Just check whether the notebook works, and quit by Ctrl + C.
- \$ sudo -H pip3 install jupyterlab
- \$ jupyter lab
 - Just checking, Ctrl + C.
- \$ jupyter notebook --generate-config
- \$ Is -I -a
 - Check .jupyter directory
- \$ jupyter notebook password
- \$ cd .jupyter/
- \$ openssl req -x509 -nodes -days 365 -newkey rsa:2048 -keyout mykey.key -out mycert.pem

- It asks to type your information. For example, type . for all except common name is your name.
- \$ cat jupyter_notebook_config.json
 - Copy password inside.
- \$ pwd
 - Use this directory in the following. /home/ubuntu/.jupyter
- \$ vim jupyter_notebook_config.py
 - Remove # from the following code and modify
 - c.NotebookApp.certfile = u'/home/ubuntu/.jupyter/mycert.pem'
 - c.NotebookApp.keyfile = u'/home/ubuntu/.jupyter/mykey.key'
 - o c.NotebookApp.ip = '*'
 - c.NotebookApp.password = u'[PASSWORD IN JSON]'
 - c.NotebookApp.open_browser = False
 - c.NotebookApp.port = 8888
 - c.NotebookApp.notebook_dir = '/home/ubuntu'
- \$ jupyter lab
- Go to EC2 instance page and copy IPv4 Public IP
- Open Google Chrome, and type in search window, https://[IPv4 Public IP]:8888/

Setup Airflow

- \$ sudo -H pip3 install apache-airflow
- \$ airflow info
- \$ airflow initdb
- \$ airflow webserver -p 8080
- Open Google Chrome, and type in search window, http://[IPv4 Public IP]:8080/

Use Airflow

- \$ cd airflow/
- \$ mkdir dags
- Make python file which contains dag and tasks info
- \$ airflow test DAG_ID TASK_ID YYYY-MM-DD
- \$ airflow scheduler
- Go to Airflow UI, and enable DAG

Keep running Jupyter and Airflow

- \$ screen --version
- \$ screen -S jupyter
- \$ jupyter lab

- o In a new terminal
- Ctrl + A, then D
 - Detached from the screen
- \$ screen -ls

Resource

- Ubuntu
 - https://www.digitalocean.com/community/tutorials/how-to-upgrade-to-ubuntu-16-0
 4-lts
- Jupyter
 - https://www.digitalocean.com/community/tutorials/how-to-set-up-jupyter-notebook
 -with-python-3-on-ubuntu-18-04
- Linux command
 - Screen command
 - https://linuxize.com/post/how-to-use-linux-screen/